

# Changelog for rc\_visard URCap

## 1.3.2 (2019-10-07)

- Return status from BoxPick improved
- Popup added if get/set/reset/parameter returns false
- Unnecessary start removed for SilhouetteMatch
- Offset changed to Distance in SilhouetteMatch calibration
- Grid size changed to fit the calibration grid size and not physical grid size

## 1.3.1 (2019-09-19)

- Fixed bug with wrong display of dropdown for the approach angle

## 1.3.0 (2019-09-04)

- Checkbox for termination if pose not found
- Ui improvements
- pose\_frame can be defined by user in all detection functions
- Move here button added to hand eye calibration set pose node
- All functions prefixed with rc

## 1.2.0 (2019-08-14)

- ItemPick program removed
- New feature: BoxPick
- New feature: SilhouetteMatch
- Major ui improvements in positioning of fields

## 1.1.0 (2019-06-26)

- New feature: Generic node
- Hand eye calibration supports robot mounted sensor
- Clear ip address in installation node
- Minor bugfixes and ui improvements

## 1.0.0 (2019-04-24)

- New feature: Hand-Eye-Calibration node
- New feature: ItemPick node
- New feature: rc\_visard installation node